




# Linux安装conda

<input checked="" type="checkbox"/> Favorite	<input type="checkbox"/>
<input checked="" type="checkbox"/> Archived	<input type="checkbox"/>
Area/Resource	 <u>Bioinformatics</u>
Project	 <u>Study Group</u> <u>bioinfo</u>
 Recipe Tags	

#登录服务器

```
$ ssh bio01@182.42.145.90
```

```
bio01@182.42.145.90's password:xxxxxxx
```

#设置清华镜像，安装conda

```
$ wget https://mirrors.tuna.tsinghua.edu.cn/anaconda/miniconda/Miniconda3-latest-Linux-x86_64.sh
--2024-06-09 13:13:48-- https://mirrors.tuna.tsinghua.edu.cn/anaconda/miniconda/Miniconda3-latest-Linux-x86_64.sh
Resolving mirrors.tuna.tsinghua.edu.cn (mirrors.tuna.tsinghua.edu.cn): 219.159.149.133.
Connecting to mirrors.tuna.tsinghua.edu.cn (mirrors.tuna.tsinghua.edu.cn): 80.
HTTP request sent, awaiting response... 200 OK
Length: 143808873 (137M) [application/octet-stream]
Saving to: 'Miniconda3-latest-Linux-x86_64.sh'
```

```
Miniconda3-latest-Linux-x86_64.sh 100%[=====
```

```
2024-06-09 13:13:52 (36.7 MB/s) - 'Miniconda3-latest-Linux-x86_64.sh' [143808873]
```

#安装conda

```
$ bash Miniconda3-latest-Linux-x86_64.sh
```

```
Welcome to Miniconda3 py312_24.4.0-0
```

```
In order to continue the installation process, please review the /root/.miniconda3/conda/en
```

agreement.

Please, press ENTER to continue

>>>

## END USER LICENSE AGREEMENT

Please read these Terms of Service carefully before purchasing, of Service ("TOS") are between Anaconda, Inc. ("Anaconda") and TOS govern Your access, download, installation, or use of the applicable Offering Description, and are hereby incorporated into hereby acknowledge that these TOS are binding, and You affirm and the Anaconda Offerings effective as of the date of first registration definitions not otherwise defined herein are set forth in Section install, download, or access the Anaconda Offerings.

### 1. ACCESS & USE.

1. General License Grant. Subject to compliance with these Terms, transferable, non-sublicensable, revocable, limited right to use Offering Description. If You purchase a subscription to an Offering, d, installation, or use of a specific Anaconda Offering will be ed by you in writing or electronic in connection with your Order. vant Offering Description, if applicable.

2. License Restrictions. Unless expressly agreed by Anaconda, rings available to anyone other than You or Your Users, unless expressly permitted in writing by Anaconda; (b) Use the Offerings ore or transmit material in violation of third-party privacy rights, mpt to gain unauthorized access to any Offerings or Third Party rformance of any Offerings or Third Party Services, or third-party hird Party Services in a way that circumvents a contractual usage as permitted under these TOS, a Custom Agreement, an Order or ture, function or user interface thereof except, and then solely ntent except as permitted herein or in an Order, a Custom Agreement ive with the offering by Anaconda, including republication on an ibution or resale; (h) Frame or Mirror any part of any Content or your own Internal Use and as permitted in a Custom Agreement le law, copy, disassemble, reverse engineer, or decompile an Off

features, functions or graphics of the Offering. You may not use, modify, copy, reproduce, resell, or otherwise distribute the Offering, in whole or in part, by any means or methodology, or any similar or equivalent manual process, without the prior written consent of the provider. The provider reserves the right to end any such activity. If You would like to redistribute the Offering, please contact the provider for a third party redistribution commercial license.

## 2. USERS & LICENSING.

Do you accept the license terms? [yes|no]

>>> yes

Miniconda3 will now be installed into this location:  
/home/bio01/miniconda3

- Press ENTER to confirm the location
- Press CTRL-C to abort the installation
- Or specify a different location below

[/home/bio01/miniconda3] >>>  
PREFIX=/home/bio01/miniconda3  
Unpacking payload ...

Installing base environment...

Downloading and Extracting Packages:

Downloading and Extracting Packages:

Preparing transaction: done  
Executing transaction: done  
installation finished.

Do you wish to update your shell profile to automatically initialize conda?  
This will activate conda on startup and change the command prompt to (base) >  
If you'd prefer that conda's base environment not be activated (base) >

run the following command when conda is activated:

```
conda config --set auto_activate_base false
```

You can undo this by running `conda init --reverse \$SHELL`? [yes/  
[no] >>> yes

```
no change      /home/bio01/miniconda3/condabin/conda
no change      /home/bio01/miniconda3/bin/conda
no change      /home/bio01/miniconda3/bin/conda-env
no change      /home/bio01/miniconda3/bin/activate
no change      /home/bio01/miniconda3/bin/deactivate
no change      /home/bio01/miniconda3/etc/profile.d/conda.sh
no change      /home/bio01/miniconda3/etc/fish/conf.d/conda.fish
no change      /home/bio01/miniconda3/shell/condabin/Conda.psm1
no change      /home/bio01/miniconda3/shell/condabin/conda-hook.ps1
no change      /home/bio01/miniconda3/lib/python3.12/site-packages
no change      /home/bio01/miniconda3/etc/profile.d/conda.csh
modified       /home/bio01/.bashrc
```

==> For changes to take effect, close and re-open your current :

Thank you for installing Miniconda3!

#安装成功

#激活conda

```
source ~/.bashrc
```

#conda一下

```
conda
```

```
usage: conda [-h] [-v] [--no-plugins] [-V] COMMAND ...
```

conda is a tool for managing and deploying applications, environ

options:

```
-h, --help          Show this help message and exit.
-v, --verbose       Can be used multiple times. Once for deta:
```

<code>--no-plugins</code>	Disable all plugins that are not built in
<code>-V, --version</code>	Show the conda version number and exit.

#### commands:

The following built-in and plugins subcommands are available.

#### COMMAND

<code>activate</code>	Activate a conda environment.
<code>clean</code>	Remove unused packages and caches.
<code>compare</code>	Compare packages between conda environments.
<code>config</code>	Modify configuration values in <code>.condarc</code> .
<code>content-trust</code>	Signing and verification tools for Conda
<code>create</code>	Create a new conda environment from a list of packages.
<code>deactivate</code>	Deactivate the current active conda environment.
<code>doctor</code>	Display a health report for your environment.
<code>export</code>	Export a given environment
<code>info</code>	Display information about current conda installation.
<code>init</code>	Initialize conda for shell interaction.
<code>install</code>	Install a list of packages into a specific environment.
<code>list</code>	List installed packages in a conda environment.
<code>notices</code>	Retrieve latest channel notifications.
<code>package</code>	Create low-level conda packages. (EXPERIMENTAL)
<code>remove (uninstall)</code>	Remove a list of packages from a specified environment.
<code>rename</code>	Rename an existing environment.
<code>repoquery</code>	Advanced search for repodata.
<code>run</code>	Run an executable in a conda environment.
<code>search</code>	Search for packages and display associated information.
<code>update (upgrade)</code>	Update conda packages to the latest compatible versions.

#### #设置conda下载镜像

```
conda config --add channels https://mirrors.bfsu.edu.cn/anaconda/
conda config --add channels https://mirrors.bfsu.edu.cn/anaconda/
conda config --add channels https://mirrors.bfsu.edu.cn/anaconda/
conda config --add channels https://mirrors.bfsu.edu.cn/anaconda/
conda config --set show_channel_urls
```

#查看conda安装包

```
conda list
```

# packages in environment at /home/bio01/miniconda3:

#

# Name	Version	Build	Channel
_libgcc_mutex	0.1	main	defaults
_openmp_mutex	5.1	1_gnu	defaults
anaconda-anon-usage	0.4.4	py312hfc0e8ea_100	defaults
archspec	0.2.3	pyhd3eb1b0_0	defaults

#安装了错误镜像地址：

```
conda config --add channels {{bfsu}}
```

#导致安装不成功

```
conda install fastqc -y
```

Channels:

- {{bfsu}}
- defaults

Platform: osx-arm64

Collecting package metadata (repodata.json): failed

UnavailableInvalidChannel: HTTP 404 NOT FOUND for channel {{bfsu}}

The channel is not accessible or is invalid.

You will need to adjust your conda configuration to proceed.

Use `conda config --show channels` to view your configuration's  
and use `conda config --show-sources` to view config file locations.

#删除路径

```
conda config --remove channels '{{bfsu}}'
```

#安装成功

```
conda install fastqc -y
```

Channels:

- https://mirrors.bfsu.edu.cn/anaconda/pkgs/main
- https://mirrors.bfsu.edu.cn/anaconda/pkgs/free

- <https://mirrors.bfsu.edu.cn/anaconda/cloud/conda-forge>
- <https://mirrors.bfsu.edu.cn/anaconda/cloud/bioconda>
- defaults

Platform: osx-arm64

Collecting package metadata (repodata.json): done

Solving environment: done

## Package Plan ##

environment location: /opt/anaconda3

added / updated specs:

- fastqc

The following packages will be downloaded:

package	build	
-----	-----	
fastqc-0.12.1	hdfd78af_0	11.1 MI
font-ttf-dejavu-sans-mono-2.37	hd3eb1b0_0	33!
fontconfig-2.14.1	hee714a5_2	254 KI
gdbm-1.18	h8fe7016_4	141 KI
openjdk-11.0.13	h98b2900_0	164.3 MI
perl-5.34.0	h1a28f6b_2	14.0 MI
-----	-----	
Total:		190.1 MI

The following NEW packages will be INSTALLED:

fastqc	anaconda/cloud/bioconda/noarch::fastqc-0.12.1
font-ttf-dejavu-s~	anaconda/pkgs/main/noarch::font-ttf-dejavu-s~
fontconfig	anaconda/pkgs/main/osx-arm64::fontconfig-2.14.1
gdbm	anaconda/pkgs/main/osx-arm64::gdbm-1.18-h8fe7016_4
openjdk	anaconda/pkgs/main/osx-arm64::openjdk-11.0.13
perl	anaconda/pkgs/main/osx-arm64::perl-5.34.0-h1a28f6b_2

Downloading and Extracting Packages:

Preparing transaction: done

Verifying transaction: done

Executing transaction: done

#运行fastqc --help查看是否安装成功

fastqc --help

#查看conda环境

conda info --envs

# conda environments:

#

base \* /opt/anaconda3

# 新建conda环境, 用python3

conda create -n rna-seq python=3 fastqc trimmomatic -y

Channels:

- <https://mirrors.bfsu.edu.cn/anaconda/pkg/main>
- <https://mirrors.bfsu.edu.cn/anaconda/pkg/free>
- <https://mirrors.bfsu.edu.cn/anaconda/cloud/conda-forge>
- <https://mirrors.bfsu.edu.cn/anaconda/cloud/bioconda>
- defaults

Platform: osx-arm64

Collecting package metadata (repodata.json): done

Solving environment: done

## Package Plan ##

environment location: /opt/anaconda3/envs/rna-seq



added / updated specs:

- fastqc
- python=3
- trimmomatic

The following packages will be downloaded:

package	build	
-----	-----	
bzip2-1.0.8	h80987f9_6	129 KI
ca-certificates-2024.3.11	hca03da5_0	128 KI
expat-2.6.2	h313beb8_0	150 KI
freetype-2.12.1	h1192e45_0	570 KI
icu-73.1	h313beb8_0	25.4 MI
libcxx-14.0.6	h848a8c0_0	965 KI
libffi-3.4.4	hca03da5_1	120 KI
libiconv-1.16	h80987f9_3	735 KI
libpng-1.6.39	h80987f9_0	283 KI
libxml2-2.10.4	h0b34f26_2	638 KI
ncurses-6.4	h313beb8_0	884 KI
openssl-3.0.13	h1a28f6b_2	4.3 MI
pip-24.0	py312hca03da5_0	3.3 MI
python-3.12.3	h99e199e_1	14.0 MI
readline-8.2	h1a28f6b_0	353 KI
setuptools-69.5.1	py312hca03da5_0	1.3 MI
sqlite-3.45.3	h80987f9_0	1.2 MI
tk-8.6.14	h6ba3021_0	3.3 MI
trimmomatic-0.39	hdfd78af_2	144 KI
tzdata-2024a	h04d1e81_0	116 KI
wheel-0.43.0	py312hca03da5_0	140 KI
xz-5.4.6	h80987f9_1	371 KI
zlib-1.2.13	h18a0788_1	91 KI
-----		
Total:		58.4 MI

The following NEW packages will be INSTALLED:

bzip2	anaconda/pkgs/main/osx-arm64::bzip2-1.0.8-l
ca-certificates	anaconda/pkgs/main/osx-arm64::ca-certificat
expat	anaconda/pkgs/main/osx-arm64::expat-2.6.2-l
fastqc	anaconda/cloud/bioconda/noarch::fastqc-0.1
font-ttf-dejavu-s~	anaconda/pkgs/main/noarch::font-ttf-dejavu
fontconfig	anaconda/pkgs/main/osx-arm64::fontconfig-2
freetype	anaconda/pkgs/main/osx-arm64::freetype-2.1
gdbm	anaconda/pkgs/main/osx-arm64::gdbm-1.18-h8
icu	anaconda/pkgs/main/osx-arm64::icu-73.1-h31
libcxx	anaconda/pkgs/main/osx-arm64::libcxx-14.0.
libffi	anaconda/pkgs/main/osx-arm64::libffi-3.4.4
libiconv	anaconda/pkgs/main/osx-arm64::libiconv-1.1
libpng	anaconda/pkgs/main/osx-arm64::libpng-1.6.3
libxml2	anaconda/pkgs/main/osx-arm64::libxml2-2.10
ncurses	anaconda/pkgs/main/osx-arm64::ncurses-6.4-l
openjdk	anaconda/pkgs/main/osx-arm64::openjdk-11.0
openssl	anaconda/pkgs/main/osx-arm64::openssl-3.0.:
perl	anaconda/pkgs/main/osx-arm64::perl-5.34.0-l
pip	anaconda/pkgs/main/osx-arm64::pip-24.0-py3:
python	anaconda/pkgs/main/osx-arm64::python-3.12.:
readline	anaconda/pkgs/main/osx-arm64::readline-8.2
setuptools	anaconda/pkgs/main/osx-arm64::setuptools-6
sqlite	anaconda/pkgs/main/osx-arm64::sqlite-3.45.:
tk	anaconda/pkgs/main/osx-arm64::tk-8.6.14-h6l
trimmomatic	anaconda/cloud/bioconda/noarch::trimmomatic
tzdata	anaconda/pkgs/main/noarch::tzdata-2024a-h0
wheel	anaconda/pkgs/main/osx-arm64::wheel-0.43.0
xz	anaconda/pkgs/main/osx-arm64::xz-5.4.6-h80
zlib	anaconda/pkgs/main/osx-arm64::zlib-1.2.13-l

Downloading and Extracting Packages:

```
Preparing transaction: done
Verifying transaction: done
Executing transaction: done
#
# To activate this environment, use
#
#     $ conda activate rna-seq
#
# To deactivate an active environment, use
#
#     $ conda deactivate
```

```
#创建成功
```

```
conda info --envs
```

```
# conda environments:
```

```
#
```

```
base                *  /opt/anaconda3
```

```
rna-seq             /opt/anaconda3/envs/rna-seq
```

```
#激活新环境
```

```
conda activate rna-seq
```

```
#关闭
```

```
rna-seq ~ git: (master)±58 (0.098s)
```

```
conda deactivate
```